Adding WFS and WMS Data to QGIS

In this guide, we will show you how to add WFS and WMS data to QGIS using a provided WFS and WMS URL from CSDI Portal.

(A) WFS

1. Open QGIS

First, open QGIS. If you don't have QGIS installed, you can download it for free from the QGIS website.

2. Add New WFS Connection

Once QGIS is open, click on the "Open Data Source Manager" button on the toolbar.



Select the tab "WFS/OGC API – Features". Click New button under Server Connections.

Q	Data Source Ma	nager WFS / OGC API - Features		N		×
	Point Cloud	Server Connections		63		
?.	Delimited Text	Connect Remove			Load	- Save
\$	GeoPackage					
.	GPS	Q				
1.	SpatiaLite	nue name Austract sqi				
Ф.	PostgreSQL					
))) ₁	MS SQL Server					
٩,	Oracle					
V	Virtual Layer					
-	SAP HANA					
Ð,	WMS/					
V	WFS / OGC API - Features					
₩						
	XYZ	Use title for layer name				
₩,	Vector Tile	✓ Only request features overlapping the view extent				
	ArcGIS REST	Coordinate Reference System				
2	GeoNode					Change
×1+			Build query	Close	Add	Help

3. Connect to WFS Service

Enter the WFS connection Name and URL provid	led, then click OK .
--	-----------------------------

lame	WFS Sample				
IRI.	https://portal.codi.env.hk/server/services/cor	omon/hl_md_1671692797539 19916/MapServer	/WFSServer		
uthent	tication				
Conf	figurations Basic				
Choor	se or create an authentication configuration				
No.4					
HON					
HOL					
		N210			
Confi	igurations store encrypted credentials in the C	QHS authentication database.			
Confi	igurations store encrypted credentials in the C	QUE authentication database.			
Confi	igurations store encrypted credentials in the C	QGIS authentication database.			
Confi	igurations store encrypted credentials in the C	QIS authentication database.			
Confi FS Op	igurations store encrypted credentials in the C ptions	QIS authentication database.			
Confi V FS Op Version	igurations store encrypted credentials in the O ptions n	QGIS authentication database.	•	Detect	
Confi (FS Op Version Max. n	igurations store encrypted credentials in the C ptions number of features	QGIS authentication database.	•	Detect	
Confi VFS Op Version Max. n	igurations store encrypted credentials in the C ptions n number of features	QGIS authentication database.	•	Detect	
Confi FS Op Version Max. n	igurations store encrypted credentials in the O ptions n number of features nable feature paging	QGIS authentication database.	•	Detect	
Confi VFS Op Version Max. n ✓ En Page si	igurations store encrypted credentials in the O ptions m number of features nable feature paging ize	QGIS authentication database.	•	Detect	
Confi VFS OI Version Max. n Vage si Igr	igurations store encrypted credentials in the C ptions n number of features nable feature paging ize nore axis orientation (WFS 1.1/WFS 2.0)	QGIS authentication database.	•	Detect	
Confi VFS OI Version Max. n ✓ En Page si _ Igr _ Inv	igurations store encrypted credentials in the C ptions n number of features nable feature paging ize nore axis orientation (WFS 1.1/WFS 2.0) vert axis orientation	QGIS authentication database.	•	Detect	

4. Add WFS Layer to Map

The available feature types from the WFS server will be retrieved and display them in the "Browser" panel. Drag and drop the feature type from "Browser" panel to "Layers" panel

punci.	
Browser	0 X
C. 😂 🝸 🖆 📀	
C:\(Windows) D:\(DATADRIVE0) GeoPackage	
PostgreSQL SAP HANA MS SQL Server	
Oracle WMS/WMTS Vector Tiles	
WZ Tiles WCS WFS / OGC API - Features	
V STOP FERRY	
Lavers	▼ ⊘ X
 ✓ ▲ ● 〒 € 1 → □ ■ □ 	
V V PopenstreetMap	

5. Result



(B) WMS

1. Add New WMS Connection

Once QGIS is open, click on the "Open Data Source Manager" button on the toolbar.

6	Untitle	ed Pro	ject —	QGIS							
F	Project	<u>E</u> dit	<u>V</u> iew	<u>L</u> ayer	<u>S</u> etti	ngs	<u>P</u> lugins	Vecto	or <u>R</u> a	aster	Ī
				3 🔇	∎a	1	5	Æ	P	5	0
		?	V., /	2		V	11.	1	B	•°°	,

Select the tab "WMS/WMTS". Click **New** button under Server Connections.

Q Data Source Man	ager WMS/WMTS				
Point Cloud	Layers Layer Order Tilesets				
Delimited Text	Connect New	F it 1	Remove		Load Save
🙀 GeoPackage	٩				
🖶 GPS	ID Name	Title	Abstract		
루 SpatiaLite					
PostgreSQL					
MS SQL Server					
📮 Oracle					
🕌 Virtual Layer					
+ SAP HANA	Image Encoding				
	Ontions				
MES 105					
API -	Tile size				
reatures	Request step size				
🗦 wcs	Maximum number of GetEasturally	io manito		10	
2017	Maximum number of Geneatorein	0 1650115		10	
+ XYZ	Coordinate Reference System			EPSG:4326 - WGS 84	• 🐁
Vector Tile	Use contextual WMS Legend				
ArcGIS REST Server	Laver name				
GeoNode	Select layer(s)				
1.				Close	Add

2. Connect to WMS Service

nectio	on Details	
ame	WMS Sample	
PT	https://portal.codi.my.hk/server/services/common/td_md_1671602707520	10016MenServer/IIIMSServer
ithen	Information	
C I		
Com	diagurations Basic	
Choo	ose or create an authentication configuration	
No 8	Authentication 👻 🖉 🖶 🔁	
Confi	figurations store encrypted credentials in the QGIS authentication database.	
Confi	figurations store encrypted credentials in the QGIS authentication database.	
Confi	figurations store encrypted credentials in the QGIS authentication database.	
Confi	figurations store encrypted credentials in the QGIS authentication database.	
Confi	figurations store encrypted credentials in the QGIS authentication database. Headers	
Confi ITP H Refere	figurations store encrypted credentials in the QGIS authentication database. Headers er	
Confi ITP H Refere	figurations store encrypted credentials in the QGIS authentication database. Headers er	
Confi ITP F Refere MS/V	figurations store encrypted credentials in the QGIS authentication database. Headers er Advanced WMTS Options	
Confi ITP H Refere A MS/V DPI-M	figurations store encrypted credentials in the QGIS authentication database. Headers er kdvanced WMTS Options Mode	all
Confi TTP F Refere MS/V DPI-M Ig	figurations store encrypted credentials in the QGIS authentication database. Headers er Advanced WMTS Options Mode gnore GetMap/GetTile/GetLegendGraphic URI reported in capabilities	all
Confi IIP H Refere MS/V DPI-M Ig Ig	tigurations store encrypted credentials in the QGIS authentication database. Headers er Advanced WMTS Options Mode gnore GetMap/GetTile/GetLegendGraphic URI reported in capabilities gnore GetFeatureInfo URI reported in capabilities	all
Confi ITP H Refere b A MS/¥ DPI- <u>M</u> Ig Ig Ig	figurations store encrypted credentials in the QGIS authentication database. Headers er Advanced WMTS Options Mode gnore GetMap/GetTile/GetLegendGraphic URI reported in capabilities gnore GetFeatureInfo URI reported in capabilities gnore axis orientation (WMS 1.3/WMTS)	all
Confi ITP I Refere A MS/V DPI-M Ig Ig Ig Ig	figurations store encrypted credentials in the QGIS authentication database. Headers er Advanced WMTS Options Mode gnore GetMap/GetTile/GetLegendGraphic URI reported in capabilities gnore GetFeatureInfo URI reported in capabilities gnore axis orientation (WMS 1.3/WMTS) gnore reported layer extents	all
Confi IIP H Refere A MS/V DPI-M Ig Ig Ig Ig Ig Ig In	tigurations store encrypted credentials in the QGIS authentication database. Headers er kdvanced WMTS Options Mode gnore GetMap/GetTile/GetLegendGraphic URI reported in capabilities gnore GetFeatureInfo URI reported in capabilities gnore axis orientation (WMS 1.3/WMTS) gnore reported layer extents nvert axis orientation	all

3. Add WMS Layer to Map

The available feature types from the WMS server will be retrieved and display them in the "Browser" panel. Drag and drop the feature type from "Browser" panel to "Layers"



4. Result

